

My server won't start or keeps crashing

What this is about

Your server is stuck on *Starting*, goes straight back to *Offline*, or crashes after running for a while. This guide walks through the usual causes in the order we check them ourselves. Most problems can be fixed without opening a ticket.

Step 1: Read the console

Go to the **Console** tab and start the server. The answer is almost always in the last 20–30 lines before it stops.

Lines from the panel itself start with `container@calagopus~`. Everything else comes from the game. Look for words like `ERROR`, `Exception`, `FATAL` or `Caused by`.

When the server crashes, the panel prints a block like this:

```
container@calagopus~ ----- Detected server process in a crashed state! -----  
container@calagopus~ Exit code: 137  
container@calagopus~ Out of memory: true
```

The **Out of memory** line is the most useful clue. Jump to *Out of memory* below if it says `true`.

Step 2: Match what you see

"Out of memory: true" (or exit code 137)

Your server used all the RAM your plan allows and was stopped.

- **Remove or disable heavy mods.** Big modpacks need much more RAM than vanilla.
- **Lower view/render distance** in your game's server config.
- **Pre-generate or trim your world** if the game supports it. Huge explored worlds use more memory.
- If you've already trimmed what you can, your plan may be too small. See [Upgrade/Downgrading Servers](#).

You can watch memory use live on the **Console** tab's resource graphs.

"Disk space is full, cannot start the server" / "Server is exceeding the assigned disk space limit"

You're out of storage. The server won't start until you free some up.

- Delete old **logs**, **crash reports** and **exported backup archives** in the **Files** tab.
- Archives you **exported to files** from the Backups tab count against your disk space, so delete them once you've downloaded them.

"Aborting automatic restart, last crash occurred less than ... seconds ago"

The server crashed twice in quick succession, so the panel stopped restarting it to avoid a crash loop. Fix the underlying crash (the lines **above** this message), then start the server manually.

Stuck on "Starting" forever

The game process is running but the panel never saw the line that means *ready*.

- Scroll the console. Is it still loading (generating the world, downloading mods)? First starts and big modpacks can take several minutes.
- If the console is still printing new lines, wait it out.
- If nothing new has appeared for a few minutes, look for an error near the end, then **Restart**.

Starts, then stops after a few seconds with no clear error

Most often a **broken config file** or a **bad mod**.

1. Think about what changed last: a mod, a config edit, a version update.
2. Undo it: remove the mod, or restore the config from a backup (on ZFS nodes, **Backups** → ... → **Browse** lets you grab a single file).
3. If you edited a JSON config, check it for a missing comma or bracket. Pasting it into jsonlint.com will point to the exact line.

Vintage Story: the console often names the mod that failed. Remove it from the **Mod Browser** → **Installed** tab and try again. If the panel shows a **Missing mod dependencies** banner, install the listed mods first.

"Address already in use" / "Failed to bind to port"

Your game config is set to a port that isn't yours. Go to the **Network** tab to see your assigned ports, and make sure your game's config uses the **primary** one. Most games read it from the **Startup** tab automatically; remove any port you hard-coded in config files.

Server installed wrong or is badly broken

Settings → **Reinstall Server** re-runs the original setup.

Take a backup first. Reinstalling can delete or overwrite files. If you switch on "*delete all files of this server*", it wipes everything.

Step 3: The server crashes, but only sometimes

- **Crashes restart on their own.** After a crash the panel restarts your server automatically. It only gives up if it crashes again straight away (see the *Aborting*


automatic restart message above).

- **Check Auto-Start.** **Settings** → **Auto-Start** controls what happens after we restart the machine your server runs on (for maintenance, for example). **Unless Stopped** (the default) brings it back up unless you'd stopped it yourself. **Always** brings it back regardless.
- **Get notified.** A schedule with a **Crash** trigger can send you a Discord message. See [Schedules](#).
- **Server hangs when stopping?** Turn on **Settings** → **Auto-Kill** so a server that won't shut down cleanly gets force-stopped after a set number of seconds.

Step 4: Still stuck? Open a ticket

Include these so we can help quickly:

1. **Debug Information** from the **Settings** tab: Node, Location and Server UUID. Click each field to copy it.
2. **What changed** right before it broke (mod, update, config edit).
3. The **last 50 or so lines of the console** around the crash. Copy them as text, or take a screenshot.
4. Roughly **when** it started happening.



You don't need to send your password or any files. We can see your server from our side.

Revision #4

Created 2026-10-23 14:18:32 UTC by Brandon F

Updated 2026-10-23 15:21:55 UTC by Brandon F